


Windows and Macintosh

Installation and Setup Guide



for

**TNTmips, TNTedit,
and TNTview**

Contents

Key and License Information	4
Overview	5
TNTgis Professional Software	6
TNTmips Free	7
TNTmips Basic	8
System Configuration	9
Windows	9
Mac OS X	9
Install on Windows	10
Installing from the DVD	10
Install Software	11
Install Documentation	13
Sample Data	14
TNTatlas (standalone version)	14
Install HASP System Driver (Pro)	15
Attach Software License Key (Pro)	16
Start Your TNTgis Software.....	16
Configure License	17
Install on Mac OS X	18
Install Software	18
Documentation	20
Sample Data	21
Start Your TNTgis Software.....	21
Configure License	22
Install HASP System Driver (Pro)	22
Attach Software License Key (Pro)	23
X11 X Window System	23
Languages and Fonts	24
Interface Language	24
Interface Fonts	24
Text Entry in Your Language	25
Network Licenses	27
Network License Setup	27
Sentinel HASP Admin Control Center	27
Trouble-Shooting	29

Releases and Updates30
 New Releases30
 Error Reports30
 Updates31
 Development Version32
 Upgrades33
License Agreement34
Index36

IMPORTANT: Your software license key IS your TNTgis professional product. Without your key, you can run only the Free and computer-locked Basic versions of TNTgis. Therefore, you should take steps to safeguard your key, even as you take normal precautions to safeguard other valuable possessions.

Insure your TNTgis software license key for theft or loss.

If you lose a diamond ring, the jeweler does not give you a new one. If you lose your key, MicroImages does not give you a new one. Keys are very sensitive to spurious electric current and surges, such as static discharge, so be careful when you handle the key. Do not apply force when attaching or removing a key. A damaged key that is returned to MicroImages will be replaced for a nominal charge.

MicroImages software support engineers are ready to help you with TNTgis installation, setup, and operational problems. If you are using the TNTgis professional software, contact us at:

Software Support: (402) 477-9562
 FAX: (402) 477-9559
 Email: tech@microimages.com

If you are using the Basic or Free versions of TNTgis, ask for help from your campus computer lab supervisor or your organization's computer support and training specialists. TNTmips Basic and Free users may contact MicroImages directly (preferably by email or FAX), but our support staff gives priority to our professional clients.

13 January 2015

Key and License Information

MicroImages distributes the TNTgis products with various kinds of license options. You may use your TNTgis products only according to the type of license you have.

- (1) **TNTmips/edit/view Professional Portable License.** One software license key attaches to the computer and permits one user at a time to use the professional version of the licensed TNTgis software on that computer. The key may be moved from computer to computer. The TNTgis software may be copied onto multiple computers. The Portable License is enabled by the HASP license key, which is available only from MicroImages or a MicroImages reseller.
- (2) **TNTmips/edit/view Professional Network License.** A software license key attaches to the networked computer that acts as a license server. The software may be copied onto multiple computers on the network, and multiple users (up to the number of seats purchased) can run any of the TNTgis software concurrently on this network. The TNTgis Network License is enabled on the license-server computer with a NetHASP software license key, which is available only from MicroImages or a MicroImages reseller.
- (3) **TNTmips Basic Computer-Locked License.** No software license key is required. One user at a time can run the Basic version of any TNTgis software (TNTmips, TNTedit, TNTview) on the computer where it was installed. *This license cannot be transferred to another computer.*
- (4) **TNTmips Basic Portable License.** A software license key attaches to the computer to enable one user at a time to run the Basic version of any TNTgis software (TNTmips, TNTedit, TNTview). This key can be moved from one computer to another where TNTmips Free is installed and used to authorize TNTmips Basic to run on the computer to which the key is currently attached. When the key is removed from a machine, the installed TNTgis products will revert to TNTmips Free authorization.
- (5) **TNTmips Free License.** No software license key is required, and one user at a time can run the Free version of any installed TNTgis software (TNTmips, TNTedit, TNTview) on this computer. The software may be copied onto multiple computers and used on each.

Overview

Welcome to professional GIS, image processing, and desktop cartography at its best. The TNTgis software family from MicroImages, Inc. is the most innovative and technically sophisticated professional software for geospatial data management and analysis available today. A host of professionals in over 120 nations use TNTgis software for production tasks in a wide variety of disciplines.

TNTgis software can be used on computers running Windows (8, 7, Vista, or XP) or Mac OS 10.5 or later. TNTgis software is available in 64-bit and 32-bit architectures for both platforms. Your computer should have at least 1 GB of RAM and at least 1 GB of free hard drive space. MicroImages recommends using the TNTgis products with multiple monitors. TNTgis software can be installed from the DVD (requiring a DVD drive) or from files downloaded from MicroImages.com.

Install and set up the TNTgis software according to the on-screen instructions in the setup program and the supplemental information in this booklet. The TNTgis professional products require a software license key supplied by MicroImages. The software license key attaches to a USB port on your computer and authorizes your TNTgis professional software for the product and license level purchased. TNTmips Basic requires either a software license key or a computer-locked license. TNTmips Free does not require a software license key.

Whether you use the TNTgis Professional software, TNTmips Basic, or TNTmips Free, the general installation sequence is:

1. Configure and optimize your computer,
2. Install the TNTgis software, documentation and license key driver (for the Professional products),
3. Install the software license key (if needed)
4. Configure the license level (TNTmips Free and Basic) and select the interface language and font

Professional clients may contact MicroImages software support:

Phone: (402) 477-9562,
FAX: (402) 477-9559, or
email: tech@microimages.com

TNTmips Basic and Free users should contact the computer lab administrator at their school or company for technical support for installation problems.

TNTgis Professional Software

(TNTmips, TNTedit, TNTview)

The TNTgis software family from MicroImages provides advanced GIS, image processing, desktop cartography, terrain analysis, and geospatial analysis on Windows and Mac computers. The TNTgis software family includes TNTmips, TNTedit, TNTview, and TNTatlas.

TNTmips

TNTmips is an advanced Geographic Information System that integrates display and processing of map data, imagery, and terrain data along with the creation and management of associated relational databases. TNTmips provides all the tools needed to create, edit, georeference, interpret, and publish any type of geospatial data (image, vector, CAD, shape, LIDAR, and TIN). You can use geodata in many native formats and import and export many more. TNTmips also includes a powerful geospatial scripting language (SML) to let you automate workflows and create custom processes.

TNTmips includes all the capabilities of TNTedit and TNTview. It also includes TNTatlas, a free viewer for images, map data, and electronic atlases assembled in TNTmips.

TNTedit

TNTedit provides interactive tools to display, georeference, create, and edit images, map data, and terrain data and to manage associated relational databases. TNTedit includes all of the display capabilities of TNTview and also provides import/export and geospatial scripting capabilities.

TNTview

TNTview is a professional product for viewing and interpreting geospatial data in a variety of forms (image, vector, CAD, shape, LIDAR, and TIN). You can view geodata in 2D, stereo, and 3D perspective, and view and edit associated relational databases. TNTview also provides import/export and geospatial scripting capabilities.

Software License Key

Use of any of the TNTgis Professional software products requires a software license key provided by MicroImages: a single-user portable key or a floating network license key allowing a set number of concurrent users on a network (see page 4). The software license key attaches to a USB port on your computer and is individually programmed to work with your



product, license level, and version. **Your license key IS your TNTgis product, so you should take care when handling the key to prevent damage, safeguard it from theft, and insure the key from loss, theft, or damage** (see note on page 2). Attached to your key via a chain is a tag with your product serial number; do not remove the tag from the USB key.

TNTmips Free

TNTmips Free is the free version of the TNTgis software. TNTmips Free has the same features and functions as the TNTgis professional software products with the following exceptions:

- creation and management of tilesets, job processing, LIDAR management and classification, and use of the SML geospatial scripting language are not included
- export is limited to one object at a time
- data objects are limited in size:
 - Raster objects: 1,000,000 cells with a maximum dimension of 10,000 (such as 10,000 x 100, 1,000 x 1,000, or 400 x 2,500)
 - Vector objects: 1,500 points, 1,500 lines, 500 polygons, 1,500 labels
 - Shape objects: 500 elements
 - CAD objects: 500 elements
 - TIN objects: 1,500 nodes
 - Database objects: 1,500 records per table
 - LIDAR points: 500,000 elements
 - Size of Prints: A3 / 12 x 17 inches

These size limitations are designed to provide you with enough capability to accomplish small projects in lab settings where there is no need for the full production capabilities of the professional TNTgis software products.

TNTgis project materials prepared or modified in TNTmips Free can be used with the professional TNTgis software and TNTmips Basic.

TNTmips Free requires no software license key and has no time limit. You are encouraged to copy and widely share TNTmips Free. You can download TNTmips Free from www.microimages.com/downloads/tntmips.htm.

If you are installing TNTmips Free, follow the installation instructions for the professional products. The installation process installs the same executables for TNTmips Free as it does for the TNTgis professional software.

If you remove the Software License Key from a computer running TNTmips Pro, you can switch to TNTmips Free mode by choosing Configure License from the TNTmips Help menu.

Upgrade TNTmips Free to a Full License

If you like what you see of the TNTgis software family with TNTmips Free, contact MicroImages or an authorized MicroImages reseller to purchase a professional TNTgis system (TNTmips Pro, TNTedit Pro, or TNTview Pro).

TNTmips Basic

TNTmips Basic is the very low cost version of the TNTgis software family (TNTmips, TNTedit, and TNTview). The TNTmips Basic products have the same features and functions as the TNTgis professional products, with the following exceptions:

- creation and management of tilesets, job processing, and LIDAR management and classification are not included
- scripting is limited to database queries and adding custom tools and macro functions to Views
- export is limited to one object at a time
- data objects are limited in size:

Raster objects: 4,000,000 cells with a maximum dimension of 20,000 (such as 2,000 x 2,000 or 1,000 x 4,000).

Vector objects: 3,000 points, 3,000 lines, 1,000 polygons, 3,000 labels

Shape objects: 500 elements

CAD objects: 500 elements

TIN objects: 1,500 nodes

Database objects: 1,500 records per table

LiDAR points: 2,000,000 elements

Size of Prints: A3 / 12 x 17 inches

To install TNTmips Basic you must first install TNTmips Free. If you decide you want support for larger projects, you can upgrade to TNTmips Basic by registering and paying for your upgrade on-line using a credit card. You are then issued an activation code that you can use to upgrade TNTmips Free to TNTmips Basic and create a computer-locked license. If you cannot make an on-line payment or if you want multiple licenses, you can purchase prepaid activation codes from an authorized MicroImages reseller or directly from MicroImages. You can also request a portable TNTmips Basic license authorized by a software license key. For more information on TNTmips Basic see www.microimages.com/products/tntmipsbasic/.

Upgrade TNTmips Basic to a Full License

If you like what you see of the TNTgis software family with TNTmips Basic, contact MicroImages or an authorized TNT reseller to purchase a professional TNTgis system (TNTmips Pro, TNTedit Pro, or TNTview Pro).

System Configuration

The first step in installing TNTgis software is to configure the hardware and operating system of your computer. After you complete this step, proceed to the Installation section for either Windows or Mac OS X.

Multiple Monitors. If you run TNTgis software with multiple monitors, your Primary monitor should be on the left. So for example, under Windows, use the Display Properties dialog to define the left-right positions of your Primary and Secondary monitors. On the Mac, use the Arrangement panel of the Hardware/Displays System Preferences.

Windows

To use TNTgis software with Windows 8, 7, Vista, or XP your computer needs at least 1 GB of RAM and about 1 GB of free hard drive space. The TNTgis products work well with the default Windows configuration. MicroImages does not recommend that you change any default Windows configuration settings before installing your TNTgis software. Windows memory management and hardware device controller settings should give an optimal performance environment for TNTgis software.

Mac OS X

To use TNTgis software with Mac OS X your computer needs an Intel CPU, at least 1 GB of RAM and about 1 GB of free hard drive space. The TNTgis software products for Mac require that you use OS X 10.5 or later and X11 2.1 or later. The free X11 application (The X Window System) from the XQuartz project was provided with Mac OS X through version 10.7, but must be downloaded and installed separately for Mac OS X 10.8 and later. If you do not have X11, your first launch of TNTgis software prompts the Mac OS to open a window noting the request to access X11 and providing the option to download and install it (see page 23 for details).

MicroImages does not recommend that you change any default hardware or memory configuration settings before installing TNTgis software. Mac OS X memory management and hardware device controller settings should give an optimal performance environment for the TNTgis products.

Install on Windows

The second step in installing TNTgis software is to run the installation program. If you are installing a new version of TNTgis over an existing version, refer to the chapter **Upgrades and Updates**.

If you are installing TNTmips Pro, TNTedit Pro, or TNTview Pro, **do not attach the software license key (dongle) prior to installation.**

You can install the TNTgis software from a DVD or download the installation program from microimages.com.

Installing from the DVD

Insert the TNTgis DVD into the DVD drive on your computer. If an AutoPlay window appears, press the *Open folder to view files* button (see illustration below left). If no AutoPlay window appears, use Windows Explorer to navigate to the DVD drive and open the main folder on this disc.



Name	Date modified	Type
doc	1/9/2015 3:51 PM	File folder
hasp	10/17/2014 4:32 PM	File folder
setup32	1/9/2015 3:11 PM	File folder
setup64	1/9/2015 3:33 PM	File folder
tntatlas	1/9/2015 3:43 PM	File folder
autorun.inf	10/17/2014 4:26 PM	Setup Information
install.pdf	11/21/2014 9:18 AM	Adobe Acrobat D...
mi.ico	10/29/2014 2:44 PM	Icon
readme.txt	11/6/2014 12:43 PM	Text Document
SampleData.zip	1/9/2015 3:57 PM	WinRAR ZIP archive
setup.exe	1/9/2015 2:35 PM	Application

Double-click on the **setup** program in the root folder of the DVD (see illustration above right). The MicroImages TNTgis Installer window then opens (right). You use this window to install the TNTgis software, optional documentation, and the HASP System Driver that is needed to support use of the software license key.




MicroImages provides the TNTgis software family in both 64-bit and 32-bit architectures for Windows, each with its own installation program. If you are

running a 32-bit Windows OS (XP or Vista), install only the 32-bit TNTgis software. If you are running a 64-bit Windows OS (Vista or later), you can install the 64-bit or 32-bit TNTgis software, or both (in separate installation operations). Some external file formats may not be supported for use, import, or export in the 64-bit TNTgis software.

All of the TNTgis software products for each system architecture use the same installer. The product (TNTmips, TNTedit, or TNTview) and license level (Pro, Basic, or Free) that you can use after installation are controlled by the software license key or TNT Basic computer-locked license.


Install Software

If you are installing from the TNTgis DVD, choose *TNTgis (32-bit)* or *TNTgis (64-bit)* from the TNTgis Installer window and press the *Install* button.



Windows for Intel and AMD CPUs: Windows 8, Windows 7, Vista, XP		
TNTmips 32-bit	144 Mb	TNT_2015_App_Win32_20141029.exe
TNTmips 64-bit	124 Mb	TNT_2015_App_Win64_20141029.exe

If you are downloading the installation program, choose the TNTmips 64-bit or TNTmips 32-bit installer from www.microimages.com/downloads/tntmips.htm. After downloading, double-click on the icon for the installer file.





Depending on your Windows security settings, a User Account Control window may then open, asking if you want to allow the installer to make changes to your computer. Press the *Yes* button on this window to proceed with the installation.

If you are logged in to Windows as a user without administrator privileges, the User Account Control window also requires that you enter the password for the administrator account on the computer. If you don't know the administrator password, request assistance from your organization's computer services department.





InstallShield Wizard

The Windows installation process uses the InstallShield Wizard, which leads you through the installation steps. A Setup Status window is shown as InstallShield prepares the installer, then a Welcome window is shown. Press the *Next* button on this window to continue. You can press the *Back* button on any subsequent wizard window to go back to the previous step.




License Agreement The next window to appear is the TNTgis license agreement. The complete license agreement is on pages 34 and 35 of this booklet or you can use the Print button if you want a printed copy in a larger format. You must click on the *Yes* button to proceed with the installation. Clicking on the *No* button cancels the setup process.

Customer Information This window asks for your name and your company's name and lets you indicate whether the installed product can be run by all users of the computer or only you as established by login name. You must enter a company or organization name to activate the *Next* button.



Choose Destination Location MicroImages recommends that you accept the default destination suggested, but you can click on the *Browse* button to select a different destination folder if desired.

Select Features This window lets you select the features you want to install. The application and all available interface language translation packages are selected by default. You can deselect any of the translation packages that will not be needed at your site.



Start Copying The next window allows you to review the installation settings before proceeding. Press the *Next* button to proceed with the installation of the TNTgis software. An Installation Complete window is shown when the installation procedure is complete. Press the *Finish* button on this window to close.


If you are installing from the DVD, the MicroImages TNTgis Installer window may not automatically reappear after the product installation. In this case you can click on its icon in the Windows taskbar to restore the window to the screen.

Install Documentation

If you have an Internet connection, TNTgis Technical Guides, Tutorials, and Quick Guides are automatically available from the TNTmips/TNTedit/TNTview Help menu and from the Quick Help for individual processes. If you prefer, you can install the complete set of documentation files on your computer for direct local access. The Tutorials provide step-by-step instructions for major processes in the TNTgis software. Technical Guides summarize the capabilities of individual processes and explain the process interface and settings. Quick Guides provide quick how-to's and power tips.

The TNTgis documentation totals approximately 420 MB. If you are installing both 32-bit and 64-bit versions of TNTgis software, you only have to install one copy of the documentation; it is automatically accessed by both TNTgis installations.

The installed TNTgis documentation comes with a pre-built search index. You can also search the documentation from the MicroImages web site.



If you are installing from the DVD, select *Documentation* from the TNTgis Installer window and press the *Install* button. If you have downloaded the TNTgis software installer, you can also download the documentation installer from the TNTmips downloads page at microimages.com. After downloading, double-click on the documentation installer icon button. Authorize the installation in the User Account Control window, then follow the instructions in the InstallShield wizard to complete the documentation installation.

Sample Data

MicroImages provides a collection of sample geospatial datasets that can be used with the TNTgis software family. These datasets are also referenced in the step-by-step lessons in the Tutorials.

The sample data is provided on the TNTgis DVD in a ZIP file, **SampleData.zip**, at the root level of the disc. You can also download the ZIP file from www.microimages.com/documentation/tutorialData.htm

readme.txt	10/21/2014 10:16 ...	Text Document
SampleData.zip	10/22/2014 10:57 ...	WinRAR ZIP archive

Copy or download the ZIP file to your hard drive and extract the archive. The archive expands into a number of separate dataset folders, so MicroImages recommends that you place the ZIP file in a separate folder before extracting, or use the option to extract to a folder named after the archive (if available in your ZIP software).

TNTAtlas (standalone version)

The free TNTAtlas geodata viewer is installed automatically as part of the TNTgis software. If you plan to distribute electronic atlases for use with TNTAtlas, you may wish to test your atlases on a computer with only the TNTAtlas software. If so, you can use the TNTgis DVD to install the standalone TNTAtlas software on your test computer. You can also download the TNTAtlas installer from www.microimages.com/products/tntatlas/.

Install HASP System Driver

(Professional License installed from DVD)


A professional license for TNTmips, TNTedit, and/or TNTview is enabled by a USB software license key that requires the Sentinel HASP driver to be installed.

- If you are installing TNTmips Free or TNTmips Basic, no license key or driver are required; skip this section and proceed directly to the section entitled Start Your TNTgis Software.
- If you are installing the professional TNTgis software from a downloaded installer, skip directly to the section entitled Start Your TNTgis Software. The HASP driver will be installed during the startup procedure.

IMPORTANT: do not attach the software license key to your computer until **after** you have installed the HASP driver.

The Sentinel HASP Driver provided by MicroImages for the professional products must be installed before you attach the software license key to your computer. If you plug in the key before installing this driver, Windows will automatically install its own driver for the device instead.

If you are installing the professional TNTgis software from the DVD, choose the *HASP System Driver* option from the TNTgis Installer window and press the *Install* button. After you authorize the installation in the User Account Control window, the Sentinel Runtime Setup wizard opens to step you through the installation. Press the *Next* button on the initial window to continue.



The next wizard window presents the SafeNet Sentinel LDK Product End User License Agreement (illustrated on the previous page). Turn on the radiobutton labeled *I accept the license agreement* and press the *Next* button to continue.

A *Ready to Install the Application* screen is then shown in the wizard. Press the *Next* button to continue with the driver installation. When the installation is complete, press the *Finish* button on the wizard window. You may need to restart Windows in order for the driver to be loaded properly.


Attach Software License Key (Professional License)

If you have installed TNTmips Pro, TNTedit Pro, or TNTview Pro from the TNTgis DVD, and installed the HASP driver, you should now carefully plug the TNTgis software license key into any convenient USB port on your computer. Do not attach the key unless you have already installed the HASP driver.




Start Your TNTgis Software


You can now start your TNTgis software for the first time. From the Windows Start menu, click on All Programs, then scroll down and click on the MicroImages folder in the list to expand it. The expanded contents show an entry for the TNTmips version (e.g., 2015) you have installed. If your license allows, you can start TNTmips (or TNTmips Free) from this menu entry. You can also expand the TNTgis [version number] folder to launch TNTedit or TNTview.



From the Window 8 Apps screen, locate the MicroImages section and double click the icon for your TNTgis software product.



A Question window appears to allow you to transfer settings from a previous TNTgis software installation. These settings include stored process preferences as well as the last-used paths to data in



various processes. If you press the *Yes* button, a Browse For Folder window opens to allow you to choose the settings folder from a specific previous TNTgis version. Press the *No* button if you don't have a previous TNTgis installation or you don't want to transfer settings.



Configure License

If you are installing TNTmips Free or Basic, or the professional TNTgis software from a downloaded installer (HASP driver and software license key are not yet installed), the TNTgis Software License Configuration window opens next. The radiobuttons on this window let you choose a license level for TNTmips (or the professional product you have purchased: TNTmips, TNTedit, or TNTview).

If you are installing Free or Basic, choose *Free (no license required)*. Basic users must initially run TNTmips Free, then choose the *Upgrade to TNTmips Basic* option from the Help menu (see the upgrade instructions at www.microimages.com/products/tntmipsbasic/how-to-upgrade.htm).



If you are installing the professional TNTgis software from a downloaded installer, choose *Professional (local or network HASP key)*.

When you press the *OK* button, you will be prompted to install the Sentinel HASP System Driver using the Sentinel Runtime Setup wizard (see page 15). After the HASP driver is installed, you will be prompted to plug the TNTgis software license key into any convenient USB port on your computer.

Install on Mac OS X

The second step in installing the TNTgis software is to run the installation program. If you are installing a new version of TNTgis software over an existing version, refer to the chapter **Upgrades and Updates**.

If you are installing TNTmips Pro, TNTedit Pro, or TNTview Pro, **do not attach the software license key (dongle) prior to installation.**

You can install the TNTgis software from a DVD or download the installation program from microimages.com.

MicroImages provides the TNTgis software in both 64-bit and 32-bit architectures for Mac OS X, each with its own installation program. The versions of Mac OS X under which you can run the TNTgis products all support 64-bit programs, so MicroImages recommends that you install the 64-bit TNTgis software.

All of the TNTgis products for each system architecture on Mac OS X use the same installation program. The product (TNTmips, TNTedit, or TNTview) and license level (Pro, Basic, or Free) that you can use after installation are controlled by the software license key or TNT Basic computer-locked license.

Install Software

If you are installing from the DVD, you can choose between 64-bit and 32-bit programs during the installation sequence. If you are downloading the installation program, choose the TNTmips 64-bit or 32-bit installer from www.microimages.com/downloads/tntmips.htm.

Mac: OS 10.10, 10.9, 10.8, 10.7 or 10.6		
TNTmips 32-bit	192 Mb	TNT_2015_App_Mac32_20150107.dmg
TNTmips 64-bit	173 Mb	TNT_2015_App_Mac64_20150107.dmg

If you have acquired your TNTgis software on DVD, a window with contents like that illustrated to the right should appear when the DVD is inserted or when you double-click on the DVD icon on your desktop. Double-click on the icon in this screen to start the installation. If you have downloaded the TNTgis installer,





TNTgis 2015 Ap p.Wa.dmg

double-click on the installer name or icon in your Downloads folder.


Installation of software on the Mac requires administrator privileges. When you start the TNTgis installer, Mac OS X opens a window with the administrative user name and a field for entering the password.



If you don't know the administrator password, request assistance from your organization's computer services department.


The installation program for TNTgis for Mac OS X uses Installer VISE, which operates like the Apple installer for Apple software products, providing a wizard interface to lead you through the installation.

License Agreement The first window to appear is the TNTgis license agreement. The complete license agreement is on pages 34 and 35 of this booklet or you can use the *Print* button if you want a printed copy in a larger format. When you press the *Continue* button, a panel drops down from the top of the window asking whether you agree to the terms of the license agreement. You must press the *Agree* button to proceed with the installation. After doing so, press the *Continue* button again on the License Agreement screen to proceed to the next screen.



Select Destination MicroImages recommends that you accept the default destination suggested, but you can click on the *Select Folder* button to select a different destination folder if desired. Press the *Continue* button to proceed to the next wizard screen.

Installation Type If you are installing from the TNTgis DVD, the Installation Type screen allows you to select either the 32-bit or 64-bit form of the TNTgis software to install. The list also includes entries for the Tutorial booklets and Sample Geospatial Data, which are selected by default. Each option has a  icon to the right. Click on this icon to view the installed size of each component along with additional information. The sections of this guide below entitled Documentation and Sample Data provide more detailed descriptions of these items.



If you have downloaded the TNTgis installation program, the only item available in the Installation Type screen is the 64-bit or 32-bit TNTgis component.

Press the *Install* button to proceed with the installation. When the operation is complete, a screen appears to indicate that installation was successful. Press the *Quit* button to close the installation program.

Documentation

If you have an Internet connection, the TNTgis Technical Guides, Tutorials, and Quick Guides are automatically available from the TNTgis software Help menu and from the Quick Help for individual processes. If you prefer, you can install the complete set of documentation files on your computer for direct local access. The Tutorials provide step-by-step instructions for major processes in the TNTgis products. Technical Guides summarize the capabilities of individual processes and explain the process interface and settings. Quick Guides provide quick how-to's and power tips.

The TNTgis documentation totals approximately 420 MB. The installed documentation comes with a pre-built search index. You can also search the documentation from the MicroImages web site.

As noted above, if you are installing from the TNTgis DVD you can include the documentation in the installation by accepting the default settings. If you have downloaded the TNTgis installer, you can also download the documentation installer from the TNTmips downloads page at microimages.com. After downloading, double-click on the documentation installer icon button. The Installer VISE wizard is used for installing the documentation, so the installation steps are similar to those outlined on the previous pages for the software.

Sample Data


MicroImages provides a collection of sample geospatial datasets that can be used with the TNTgis software products. These datasets are also referenced in the step-by-step lessons in the Tutorials.

As noted previously, if you are installing from the TNTgis DVD you can include the sample data in the installation by accepting the default settings. You can also download a ZIP file containing all of the documentation from www.microimages.com/documentation/tutorialData.htm

Download the ZIP file to your hard drive and extract the archive. The archive expands into a number of separate dataset folders, so MicroImages recommends that you place the ZIP file in a separate folder before extracting, or use the option to extract to a folder named after the archive (if available in your ZIP software).

Start Your TNTgis Software

Once installation is complete, you have a folder for the version of the TNTgis software you installed with icons to launch each of the TNTgis products (TNTmips, TNTedit, TNTview, and TNTatlas). You can drag the icon for your TNTgis product from this folder to the dock to provide a short cut for starting your TNTgis software.



The TNTgis folder also includes folders for your Program Files, TNTgis temporary files, sample Geospatial Analysis scripts, and geospatial data (if installed). The tutorials, Technical Guides, and Quick Guides are found in the *doc* folder within the Program Files folder.

Double-click on the icon or short cut for your TNTgis product to start it.

Configure License

The first time you start your TNTgis software, the License Configuration window appears. The menus on this window let you choose a license level for each TNTgis product (TNTmips, TNTedit, and TNTview).



If you are installing Free or Basic, choose *Free* from the menu for each product, press the *OK* button, and restart your TNTgis product to continue. Basic users must initially run TNTmips Free, then choose the *Upgrade to TNTmips Basic* option from the Help menu (see the upgrade instructions at www.microimages.com/products/tntmipsbasic/how-to-upgrade.htm).

If you are installing the professional TNTgis products, choose *Pro* from the menu for each product and press the *OK* button. If this is the first TNTgis installation on this computer, you will then be prompted to install the Sentinel HASP System Driver.

Install HASP System Driver (Professional License)

A professional license for TNTmips, TNTedit, and/or TNTview is enabled by a USB software license key that requires the Sentinel HASP driver to be installed.


IMPORTANT: do not attach the software license key to your computer until **after** you have installed the HASP driver.



After you have provided the administrator password for the driver installation, the HaspInstall Installer opens. A panel drops down from the top of the first screen; press the *Continue* button on this panel to return to the first screen. Press the *Continue* button on this and each subsequent screen to proceed with the installation.

The next wizard window presents the Safenet Software License Agreement. When you press the *Continue* button, a panel drops down from the top of the

window asking whether you agree to the terms of the license agreement. You must press the *Agree* button to proceed with the installation. After doing so, press the *Continue* button again on the License Agreement screen to proceed to the next screen.



A Standard Install screen is shown next in the wizard. Press the *Install* button to start the installation. When it is complete, the wizard will show a message that the installation was successful. Press the *Close* button to close the HaspInstall window.

Attach Software License Key (Professional License)

If you have installed TNTmips Pro, TNTedit Pro, or TNTview Pro from the TNTgis DVD, and installed the HASP driver, you should now carefully plug the TNTgis software license key into any convenient USB port on your computer. Do not attach the key unless you have already installed the HASP driver. You can now restart your TNT product.



X11 X Window System

TNTgis software on Mac OS X runs under the X11 X Window System. X11 was included with older versions of Mac OS X but is not included with the operating system for versions 10.8 and later. The first time you launch a TNTgis product on a Mac OS X system lacking X11, the operating system opens a window noting the request to access X11. Pressing the *Install* button on this window takes you to an Apple webpage with a link to the XQuartz project website (xquartz.macosforge.org) where you can download X11. Following the instructions in the installer to install X11 on your system.



Languages and Fonts

The last step in installing the TNTgis software is to customize the software interface by choosing an interface language and font.

Interface Language

The first time you install and start TNTmips, TNTedit, or TNTview, a Language window is initially displayed. This window provides a list of the many languages that are available for the TNTgis software interface. The default interface language is English. When you choose another language, the control labels, menu entries, and other components of the TNTgis software windows appear in the selected language.

You can open the Language window at any time to switch the TNTgis interface to a different language. In TNTmips, choose Tools / System / Language from the TNTmips menu. In TNTedit, click on the Options icon button in the TNTedit toolbar and choose Language from the menu. In TNTview, choose Options / Language from the TNTview window. The Language window in these instances includes a checkbox (turned on by default) to automatically restart the software with the new language setting when you press the OK button .




If you don't see the language you want on the menu, contact us at info@microimages.com to inquire about opportunities to become the Official Translator for your language.

Interface Fonts

The TNTgis software products can use any TrueType font on your system for the interface text. You may need to use 2-byte Unicode fonts to support your language and characters. In your TNTgis software, open the Font List Selection window to choose the font to use in the interface windows (in TNTmips, choose Tools / System / Fonts; in TNTedit, TNTview, and TNTatlas, choose Options / Setup Fonts).

In the Font List Selection window (illustrated below), select a desired font in the Available Fonts list at the top of the window and press the Add icon button to add it to the Selected list. You can add more than one font to the selected list and easily switch between them. Fonts are used in the order in which they appear in the list. (If a character being rendered is not in the first font, the next font in the list will be used for that character.) Use the icon buttons in the Selected pane to change the list order when needed.



Text Entry in Your Language


All of the TNTgis software products can use text in any language and TrueType font for map annotations, legends, labels, and database attributes. To enter text in your language you must configure your computer's interface to use your language and any required keyboard layout. To do so, follow the steps outlined below.

Windows: Install Language Pack and Font

If you have not done so already, your first step for Windows computers is to download and install the language package for your language from Microsoft. This is important if text entry in your language requires a specific keyboard layout. (Mac OS X has built-in support for many languages and their keyboard layouts.) Also make sure that you have a TrueType font that supports the character set used for your language.

Change Your OS Display Language

Set your language as the display language for your operating system and select any required keyboard layout option. In Windows, change the display language in the Region and Language window (in PC Settings in Windows 8 or the Control Panel in earlier Windows versions). In Mac OS X, use the Language and Text window (in System Preferences) to change the order of preference in the language list.



Japanese Text Input on Mac OS X

Input of text in Japanese on Mac OS X requires installing the Mac UIM package, a text input method library that is available at

<https://github.com/e-kato/macuum/>.

Activate Japanese input by pressing Shift-Space in any text entry in TNTmips (this requires setting the TNTmips interface language to Japanese). As you type, you will see a new text input area in the bottom left of the window that receives the Japanese input. Pressing the Space or up/down arrow keys allows you to scroll through the possible Kanji selections matched to your input. When you are done, press Enter to insert the Japanese text. Pressing Shift-Space again will deactivate the input method.

Network Licenses

Network (floating) licenses for both Windows and Macintosh systems are managed using the same NetHASP software license key (dongle). The administration software for network licenses presents the same interface for both platforms. Note that the license server can be on a computer that does not have any TNTgis software installed. You can also run TNTgis software from the computer to which the NetHASP key is attached if desired.

Network License Setup

1. Choose the computer that will be the license server on the network, but **DO NOT ATTACH** the NetHASP key until after the latest driver is installed.
2. Install the driver.
If you have a TNTgis DVD, run the install process with the HASP System Driver selected. If you are not going to run the TNTgis software on your license server machine itself, you do not need to install the TNTgis software on that computer. If you do not have a TNTgis DVD, the latest installer for the key driver can also be downloaded from www.microimages.com/downloads/haspDriver.htm.
3. Attach the NetHASP Key to the license server machine. Be sure the light in the key is on (solid red). The light may flash for a few seconds when the key is first attached.

On each machine that will run the TNTgis software:

1. Install the TNTgis software.
2. Install the latest HASP key driver (see step 2 above for how to get this driver).
3. Start the TNTgis software. Choose to use the HASP key if prompted. If the license manager does not work, restart the machine.

Sentinel HASP Admin Control Center

The floating network license features of the NetHASP key can be monitored and managed using the Sentinel HASP Admin Control Center software that is installed along with the latest HASP system driver for current editions of TNTgis software. The Admin Control Center software is installed in the same folder as your TNTgis software and is available from the Windows Start menu (All Programs/MicroImages/TNTgis [version]/HASP Admin Control Center) and/or from your TNTgis folder. The Admin Control Center lets you monitor the number of users and which users are currently logged in to a particular HASP key and the number of users allowed for that key. You can also use the Admin Control Center to change the number of concurrent users allowed for your floating license.

Note that this administrative software is provided by SafeNet, and MicroImages has no control over its content or operation.

HASP Keys. This option lists the HASP keys connected on both local and remote machines that are using the NetHASP key. It also provides additional information about each key (e.g., key type, version, and ID).

#	Location	Vendor	HASP Key ID	Key Type	Version	Sessions	Actions
1	WOODSTOCK3	51060	1817962800	HASP HL Net 10	3.25	-	<input type="button" value="Browse"/> <input type="button" value="Net Features"/>

Products. All the products available from HASP License Managers accessible on the network are listed. This option is also used for management of detachable licenses. Detachable licenses are not an option with TNTgis software.

#	Product Name	Vendor	Location	Actions
1	TNTmips Floating	51060	WOODSTOCK3	<input type="button" value="Features"/>

Features. This option lists features available on HASP keys currently on the network including current activity and conditions of the license. The number in the Limit column tells you how many concurrent users are authorized for the floating license while the number in the Logins column tells you how many users are currently logged in. The access column provides the machine types from which access is allowed: local machine (loc), remote clients via the network (net) and/or remote clients via terminal server display (disp). Note that all three are allowed with a TNTmips floating license.

#	Vendor ID	HASP Key ID	Feature ID	Location	Access	Counting	Logins	Limit	Detached	Restrictions	Sessions	Actions
1	51060	1817962800	0	WOODSTOCK3	Loc Net Display	Station	-	10	-	Perpetual	-	<input type="button" value="Browse"/>
2	51060	1817962800	1	WOODSTOCK3	Loc Net Display	Station	2	3	-	Perpetual	3	<input type="button" value="Browse"/>

The Limit column in the line with a Feature ID of 0 is the number of clients that can ask if a license is available at one time (here 10). The Limit column in the line with a Feature ID of 1 is how many TNTgis licenses there are (here 3).

Sessions. This option provides information about users that are logged in and their sessions. It also lets you disconnect logged in users.

ID	HASP Key ID	Location	Feature ID	Address	User	Machine	Login Time	Timeout	Actions
0000000B	1817962800	10.0.0.101	1	Local	mskndla	memvostro:1520	Fri Jul 9, 15:19:20	11:59:00	Disconnect

Update/Attach. This option is the one you use to change the number of concurrent seats available with your license. For example, if you have purchased additional seats for your TNTgis network license, MicroImages will provide a V2C (vendor to client) file with the new number of seats. You browse to and select that file and click on the Apply File button to increase the number of seats.

Access Log. This option lets you view the log entries for this license server. This log is enabled from the Configuration options.



Configuration. This option lets you designate basic settings for monitoring the activity of the machines using the floating license. Password protection settings can be viewed/specified and the password can also be changed from this page.

Diagnostics. This administration option provides information about license operation, assists in diagnosing problems, and can generate reports for technical support.

Help. For more information refer to the Help in the Admin Control Center.

Trouble-Shooting

1. Start the HASP Admin Control Center on the license server machine. Make sure it shows the NetHASP key under the HASP Keys administrative option. If not, check that the key is physically attached to the machine and that it is showing a solid red light.
2. Start the HASP Admin Control Center on the client machine with the TNTgis software installed. Make sure that it shows the NetHASP key in the list. If it does not, check the network connection (check physical connection and ping the server machine) and security settings. Your firewall may be preventing communication.

Releases and Updates

New Releases

MicroImages produces annual releases of the TNTgis software products early in the calendar year. If you have purchased annual maintenance for the new version, you can download the installers for TNTgis software and documentation from www.microimages.com. The installation process lets you select the target directory for the installation. In most cases, you should accept the new directory offered as the default.

MicroImages does NOT RECOMMEND that you install a new version over your existing version. Install the new version separately, so you will have the option of using the old version alongside the new version during a transition period. You will probably want to continue to work with familiar features for a while until you have time to learn the new features. The first time you run the new version, a startup dialog offers you the option of copying your personal settings and defaults from the previous version to the new version.

For sites using a network (floating) license, the new version should be installed on each computer that runs the TNTgis software. If the license server does not have the TNTgis software installed, no changes need to be made there.

Software License Key Authorization. When you renew your subscription to TNTgis after a release, the License Configuration window shown the first time you run the software allows you to enter an authorization code provided by MicroImages to enable your key for the new version. Enter the code exactly as it appears on the authorization notice you receive. If you renew prior to the release, the entry of an authorization code is not necessary.

Network Software License Key Authorization. When you need to authorize a network (floating) license to a new version, the authorization code needs to be entered only once, on any one of the client computers on which the TNTgis software is installed.

Error Reports

All software has errors. MicroImages responds quickly to error reports. But if we don't know about them, we can't fix them. So we encourage you to report problems that you find so we can fix them and provide an updated edition to all our users. The best method for reporting errors is to use the Contact

Support form that opens when you select Contact Support from the Help menu in your TNTgis software product. This form helps your error reporting by providing tools to assist in your error description, such as creating screen shots and movies of the steps needed to reproduce the problem. It also collects some information from your machine, such as your operating system and the version of the software you are running.


You may also report errors to our software support team using these other methods:

voice: (402)477-9562
FAX: (402)477-9559
email: tech@microimages.com

Updates

MicroImages is committed to providing error fixes to all clients in a timely fashion. The **Release Version (RV)** is the current official release of the TNTgis software. The Release Version is updated each week with all of the latest error fixes. Updated installation programs for the Release Version are posted on the MicroImages website at www.microimages.com/downloads/tntmips.htm for both Windows and Mac OS X in both 32-bit and 64-bit.

Each weekly update includes the complete TNTgis product package, which can be installed over previous editions of the same version (for example, the latest edition of TNTmips 2015 can be installed over the existing installation of TNTmips 2015). When you run the installer, a message is shown informing you that an "upgrade" of the TNTgis software will be performed. All of the previous user settings are automatically retained in this instance.



When you update a previous installation with the latest edition, you may get a message from your computer operating system that the program may not have installed correctly. This situation can occur when the update includes new components or libraries. If you see such a message, MicroImages recommends that you uninstall that version of the TNTgis software, then reinstall the update.

When you are notified by MicroImages Software Support that an error you have reported has been fixed, please download and install the latest weekly edition of the Release Version and test the process in which you encountered the error. If the problem persists, please use the Contact Support Form to report the problem with any new information pertinent to the error.

The TNTgis documentation package for the Release Version is also updated weekly. You can download the latest documentation installer from the download page noted above.

Development Version

The **Development Version (DV)** is the version of the TNTgis software currently undergoing active development, with new features and process updates added frequently. The Development Version is updated weekly on the MicroImages website at www.microimages.com/downloads/dv.htm.

If you have a professional software license authorized for the current Release Version, you can download, install, and run the DV in professional mode. (This installation is separate from your current Release Version of the TNT products.) If you do not have a current professional license, you can run the DV as TNTmips Free. All installations of the Development Version expire 30 days after their issue date and must be updated with a newer edition for continued use.


You may wish to try out the Development Version to take advantage of the new features that have been added that may be useful to you in your project work. Note that new features in the DV may not have been fully tested in all situations and with all forms of data, so these new features may not be complete and may not be as stable as those in the Release Version. Thus we urge clients who are doing mission-critical production work and facing deadlines to use the Release Version, not the Development Version, for their required tasks.

Nevertheless, MicroImages invites interested (and intrepid) clients to download and work with the Development Version. You can partner with MicroImages by reporting errors and suggesting improvements during our development phase to help keep the TNT products the most innovative and advanced products on the market.

When a new version of the TNT products is officially released, the former DV is discontinued. It may be several weeks before the new Development Version is made available on the MicroImages website. **You should uninstall the former Development Version before installing the official release version of the software.**

Upgrades

The software license key distributed with the TNTgis professional products is programmed to support the product level (TNTmips, TNTedit, or TNTview) and version number that you purchased. MicroImages makes it easy to upgrade your existing installation to a higher product level (*e.g.*, TNTedit to TNTmips). When you purchase a new product level, MicroImages sends you an **option enable code**. To apply the code to your TNTgis product, select Upgrade License from the Help menu. Enter your option enable code and press the Apply button. Your key has now been reprogrammed to support the new version or product level.



Upgrades to network licenses are supplied using V2C files rather than as option enable codes. See the **Network Licenses** chapter for additional information.

License Agreement for the MicroImages TNTgis Products

This is a legal agreement between You, the end user, and MicroImages, Inc. By opening the enclosed key package or installing the enclosed software product(s), You are agreeing to be bound by the terms of this agreement. If You do not agree to the terms of this agreement, return the unopened key package, the software disks, and the accompanying items (written materials, binders, or other containers) within 30 days from the shipping date for a full refund.

1. **GRANT OF LICENSE.** MicroImages, Inc. grants You the right to use the enclosed software program(s) (the "SOFTWARE") according to the user limits you purchased as implemented by the protection device (the software license KEY) installed on the computer. (1) If You purchased a single-user license, You may not use or attempt to use the SOFTWARE on more than one computer at a time (2) If You purchased a floating license, You may not attempt to exceed the number of simultaneous users supported by your software license KEY. (3) If You purchased no license (and therefore are using the SOFTWARE in the free mode), You may not attempt to circumvent the product design limits.

2. **COPYRIGHT.** The SOFTWARE is owned by MicroImages, Inc. and is protected by United States copyright laws and international treaty provisions. Therefore, You must treat the SOFTWARE like any other copyrighted material (e.g. a book or musical recording). License is hereby granted to duplicate and distribute the software and documentation provided that (1) You make no alterations, (2) that written credit is given to MicroImages, Inc., and (3) that all copyright notices are retained.

3. **OTHER RESTRICTIONS.** You may not reverse engineer, decompile, or disassemble the SOFTWARE or KEY. You may not rent or lease the software without prior written permission from MicroImages, Inc. You may transfer the entire KEY, SOFTWARE, updated materials, and right of license to another party provided that the recipient agrees to the terms of this Agreement, and that MicroImages, Inc. is notified of the transfer.

4. **NO WARRANTY.** This Software is being delivered to You AS IS and MicroImages makes no warranty as to its use or performance. MICROIMAGES AND ITS SUPPLIERS DO NOT AND CANNOT WARRANT THE PERFORMANCE OR RESULTS YOU MAY OBTAIN BY USE OR INABILITY TO USE THE SOFTWARE OR THE DOCUMENTATION. MICROIMAGES MAKES NO WARRANTIES, EXPRESS OR IMPLIED AS TO NON-INFRINGEMENT OF THIRD PARTY RIGHTS, MERCHANTABILITY, OR FITNESS FOR ANY PARTICULAR PURPOSE(S).

5. **WARNING.** THIS SOFTWARE IS NOT DESIGNED NOR TESTED FOR A LEVEL OF RELIABILITY SUITABLE FOR USE IN THE DIAGNOSIS OR TREATMENT OF HUMANS OR AS CRITICAL COMPONENTS IN ANY LIFE SUPPORT OR OTHER INFORMATION SYSTEMS THE FAILURE OF WHICH CAN REASONABLY BE EXPECTED TO CAUSE PERSONAL INJURY. THE SOFTWARE MAY CONTAIN DEFECTS, ERRORS, AND INACCURACIES. WHEN YOU USE IT YOU MAY ENCOUNTER INCORRECT RESULTS, ERRORS, OR ANOMALIES. YOU AGREE TO TAKE PRECAUTIONS TO OFFSET SUCH RISKS, SUCH AS TO MAINTAIN FULL BACKUPS OF STORAGE MEDIA AND TO NOT USE THE SOFTWARE WHERE PERSONAL INJURY OR PROPERTY DAMAGE MAY RESULT.

6. **LIMIT OF LIABILITY.** IN NO EVENT SHALL MICROIMAGES BE LIABLE TO YOU FOR ANY CONSEQUENTIAL OR INCIDENTAL, INDIRECT, SPECIAL, OR PUNITIVE DAMAGES, INCLUDING ANY LOST PROFITS OR OPPORTUNITIES, EVEN IF A MICROIMAGES REPRESENTATIVE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Your sole remedy for any claim is to obtain one (1) replacement copy of the

Software from MicroImages for each copy You have lawfully obtained and which You return to MicroImages. YOU AGREE THESE ARE YOUR ONLY REMEDIES EVEN IF THEY FAIL OF THEIR ESSENTIAL PURPOSE(S).

Some states may not allow the above exclusion or limitation of warranties, remedies or damages, so the above exclusions or limitations may not apply to You. This warranty gives You specific legal rights. You may have other rights which vary from state to state or province to province. For further warranty information, contact MicroImages.

7. **GOVERNING LAW.** This Agreement will be governed by the laws of the State of Nebraska, U.S.A., and by the laws of the United States of America. This Agreement will not be governed by the United Nations Convention on Contracts for the International Sale of Goods, nor by the laws of any other country or nation, the application of which is expressly excluded. You agree that the Software will not be shipped, transferred, or exported into any country or used in any manner prohibited by the United States Export Administration Act or any other export laws, restrictions, or regulations. Without limiting the foregoing, the Software may not be exported to Iran, Iraq, Libya, Syria, Cuba, or North Korea, or any nation with which the U.S. Government has embargoed trade. To gain access to the Software, You are certifying that You are not a national of one of these nations and will not permit anyone who is a citizen of one of these nations to have any access to the Software whatsoever.

8. Portions of this software incorporating MrSID functionality are provided under license from LizardTech, Inc. The MrSID software is protected by United States Copyright Law and International Treaty provisions and by U.S. Patent No. 5,710,835. Foreign patents are pending. Some of the MrSID technology was developed through a project at the Los Alamos National Laboratory (LANL) funded by the U.S. Government, managed under contract by the Regents of the University of California (University). The U.S. Government and the University have reserved rights in the Technology, including the following: (a) the U.S. Government has a non-exclusive, nontransferable, irrevocable, paid-up license to practice or have practiced throughout the world, for or on behalf of the United States, inventions covered by the University's Patent Rights, and has other rights under 35 U.S.C. § 200-212 and applicable implementing regulations and under the U.S. Department of Energy (DOE) Assignment and Confirmatory License through which the DOE's rights in the Technology were assigned to the University; (b) Under 35 U.S.C. § 203, the DOE has the right to require LizardTech to grant a non-exclusive, partially exclusive or exclusive license under U.S. Patent No. 5,710,835 in any field of use to a responsible applicant(s) upon term reasonable under the circumstances, if LizardTech does not adequately attempt to commercialize the MrSID Technology. See, 37 CFR 401.6; (c) The University makes no warranty or representation as to the validity or scope of Patent No. 5,710,835, and neither the Government nor the University have any obligation to furnish any know-how, technical assistance, or technical data in connection with MrSID software. For further information about these provisions, contact LizardTech, 821 Second Ave., Suite 1800, Seattle, WA 98104.

9. **ENTIRE AGREEMENT.** You acknowledge that You have read this Agreement, understand it and that it is the complete and exclusive statement of Your agreement with MicroImages which supersedes any prior agreement, oral or written, between MicroImages and You. No variation of the terms of this Agreement will be enforceable against MicroImages unless MicroImages gives its express consent, in writing signed by an officer of MicroImages.

19 August 2013

**This License Agreement is presented onscreen
during the TNTgis installation process.**

Advanced Software for Geospatial Analysis

MicroImages, Inc. publishes a complete line of professional software for advanced geospatial data visualization, analysis, and publishing. Contact us or visit our web site for detailed product information.

TNTmips Pro TNTmips is a professional system for fully integrated GIS, image analysis, CAD, TIN, desktop cartography, and geospatial database management.

TNTedit TNTedit provides interactive tools to create, georeference, and edit vector, image, CAD, TIN, and relational database project materials in a wide variety of formats.

TNTview TNTview has the same powerful display features as TNTmips and is perfect for those who do not need the technical processing and preparation features of TNTmips.

TNTatlas TNTatlas lets you publish and distribute your spatial project materials on CD or DVD at low cost. TNTatlas CDs can be used on any popular computing platform.

TNTmips Basic TNTmips Basic is a very low cost version of TNTmips for students and professionals with small projects with larger object size limits than TNTmips Free.

TNTmips Free TNTmips Free is a free version of TNTmips for students and professionals with small projects. You can download TNTmips Free from MicroImages' web site.

Index

activation code.....	8	new releases	30
development version	32	release version	30
documentation	13, 20, 32	sample data	14, 21
floating (network)		single-user (portable) license	4, 6
license.....	4, 6, 25-27	software license key	4, 6, 16, 23
fonts	24, 25	system configuration	9
HASP driver	15, 22	TNTmips Basic	8
Japanese on Mac OS X	25	TNTmips Free	7
languages	24-25	TNTmips Professional	6
license agreement ...	4, 12, 19, 33-34	Updates	31
license configuration	17, 22	Upgrades	33
Mac OS X installation	18-23	Windows installation	10-17
NetHasp key	27-29		

